



Products: CAM540

Firmware Version: 0.0.6004.14

Published Date: July 15, 2021

Copyright © 2016

Copyright Notice

This publication, including all photographs, illustrations and software, is protected under international copyright laws, with all rights reserved. Neither this manual, nor any of the material contained herein, may be reproduced without written consent of the author.

Disclaimer

The information in this document is subject to change without notice. The manufacturer makes no representations or warranties with respect to the contents hereof and specifically disclaim any implied warranties of merchantability or fitness for any particular purpose. The manufacturer reserves the right to revise this publication and to make changes from time to time in the content hereof without obligation of the manufacturer to notify any person of such revision or changes.

Limitations of Liability

UNDER NO CIRCUMSTANCES SHALL AVER BE LIABLE FOR DAMAGES OF ANY CHARACTER (E.G. DAMAGES FOR LOSS OF PROFIT, SOFTWARE RESTORATION, WORK STOPPAGE, LOSS OF SAVED DATA OR ANY OTHER COMMERCIAL DAMAGES OR LOSSES) RESULTING FROM THE APPLICATION OR IMPROPER USE OF THE AVER PRODUCT OR FAILURE OF THE PRODUCT, EVEN IF AVER IS INFORMED OF THE POSSIBILITY OF SUCH DAMAGES. FURTHERMORE, AVER WILL NOT BE LIABLE FOR THIRD-PARTY CLAIMS AGAINST CUSTOMER FOR LOSSES OR DAMAGES. AVER WILL IN NO EVENT BE LIABLE FOR ANY DAMAGES IN EXCESS OF THE AMOUNT AVER RECEIVED FROM THE END-USER FOR THE PRODUCT.

Content

Revision History and System Requirement	2
Important Notice	3
New Features	4
Problems Fixed	6
Known Issues	7



Revision History and System Requirement


[illegible]

Important Notice

1. Please upgrade to PTZApp2 to get better user interface. Please visit AVer web site to download the latest PTZApp2 app.
2. Smart frame uses face detection technology; please face the camera to ensure the detection accuracy. Side facial profiles are not detectable.
3. The smart frame best detection distance is up to 5meters.



New Features

Firmware Version	New Features
0.0.6004.14	N/A
0.0.6004.12	Improve local preview image (640x360 resolution) in Teams app.
0.0.6004.10	Add Visca command for supporting CL10(ExpComp/WB/WDR/Gain/Hue). Visca command for framing off. Meanwhile, it will have feedback for command accepted and completed.
0.0.6004.02	While connecting CAM540 to Teams MTR system, the RS232 port will be disabled automatically. Users can enable it again via PTZApp setting.
0.0.6002.98	1. Image settings: Original: When unplugging adaptor or rebooting, the image settings and WDR will be set back to default value. New: All the image settings and WDR will be retained after unplugging adaptor or rebooting. 2. Add UVC preset position API for Google Meet.
0.0.6002.92	Add SmartFrame preset point function. Original: Camera always goes back to central position to capture all participants and zoom in. New: Users can choose the preferred preset point direction and camera will capture all participants based on the appointed preset point 
0.0.6002.88	None
0.0.6002.84	1. Improve auto frame performance.



0.0.6002.82	1. When the camera is powered on, the settings (WDR/sharpness/brightness/contrast/saturation) for the image will revert back to factory default. 2. While executing SmartFrame function, “Framing” will be visible on the top left corner of the image screen. To remove “Framing” text, users can use PTZApp and set “On Screen Menu” OFF.
0.0.6002.78	None
0.0.6002.76	Support RS232 commands for auto framing function Support Sleep timer setting via PTZApp. Please use updated PTZApp version v. 1.4.1071.77 (MAC); . v. 1.4.1091.98 (Windows)
0.0.6002.58	Support Smart frame OFF function. Please go with PTZApp v. 1.3.1067.68 (MAC); . v. 1.3.1085.86 (Windows) to have Smart Frame “OFF” function in PTZApp. Support ZOOM Room Preset and Auto frame function
0.0.6002.46	Support people counting analytic data Support RS232 ZOOM in/out function Add. Visca command: power_inq to enter suspend mode USB2.0 mode supports 720p 、960x540 resolution
0.0.6002.24	Enhance auto frame accuracy
0.0.6000.34	Support hand-free auto smart frame function. This function has to be enabled via PTZapp (PC v.1.3.1075.77; MAC v.1.3.1060.63)
0.0.6000.26	None
0.0.6000.24	1st release with complete production functions, including 1080p/720p 60fps with 16xzoom and flip image function



Problems Fixed

Firmware Version	Problem Fixed
0.0.6004.14	Fix the UVC control issue in Win10 (such as zoom in)
0.0.6004.12	None
0.0.6004.10	None
0.0.6004.02	None
0.0.6002.98	Fix ISP occasionally failure issue
0.0.6002.92	None
0.0.6002.88	Fix some bug for working with remote control
0.0.6002.84	None
0.0.6002.82	None
0.0.6002.78	PC may not detect camera randomly
0.0.6002.76	None
0.0.6002.58	None
0.0.6002.46	None
0.0.6002.24	None
0.0.6000.34	None
0.0.6000.26	Fix. mipi config to solve random video stream error issue
0.0.6000.24	None



Known Issues

Firmware Version	Problem Fixed
0.0.6004.14	None
0.0.6004.12	None
0.0.6004.10	None
0.0.6004.02	None
0.0.6002.98	None
0.0.6002.92	None
0.0.6002.88	None
0.0.6002.84	None
0.0.6002.82	None
0.0.6002.78	None
0.0.6002.76	None
0.0.6002.58	None
0.0.6002.46	None
0.0.6002.24	None
0.0.6000.34	None
0.0.6000.26	None
0.0.6000.24	None

